# ffprobe Documentation

## **Table of Contents**

- 1 Synopsis
- 2 Description
- 3 Options
  - 3.1 Stream specifiers
  - 3.2 Generic options
  - 3.3 AVOptions
  - 3.4 Main options
- 4 Writers
  - 4.1 default
  - 4.2 compact, csv
  - 0 4.3 flat
  - 0 4.4 ini
  - 4.5 json
  - 4.6 xml
- 5 Timecode
- 6 See Also
- 7 Authors

# 1 Synopsis# TOC

ffprobe [options] [input\_url]

# 2 Description# TOC

ffprobe gathers information from multimedia streams and prints it in human- and machine-readable fashion.

For example it can be used to check the format of the container used by a multimedia stream and the format and type of each media stream contained in it.

If a url is specified in input, ffprobe will try to open and probe the url content. If the url cannot be opened or recognized as a multimedia file, a positive exit code is returned.

ffprobe may be employed both as a standalone application or in combination with a textual filter, which may perform more sophisticated processing, e.g. statistical processing or plotting.

Options are used to list some of the formats supported by ffprobe or for specifying which information to display, and for setting how ffprobe will show it.

ffprobe output is designed to be easily parsable by a textual filter, and consists of one or more sections of a form defined by the selected writer, which is specified by the print\_format option.

Sections may contain other nested sections, and are identified by a name (which may be shared by other sections), and an unique name. See the output of sections.

Metadata tags stored in the container or in the streams are recognized and printed in the corresponding "FORMAT", "STREAM" or "PROGRAM\_STREAM" section.

## **3 Options# TOC**

All the numerical options, if not specified otherwise, accept a string representing a number as input, which may be followed by one of the SI unit prefixes, for example: 'K', 'M', or 'G'.

If 'i' is appended to the SI unit prefix, the complete prefix will be interpreted as a unit prefix for binary multiples, which are based on powers of 1024 instead of powers of 1000. Appending 'B' to the SI unit prefix multiplies the value by 8. This allows using, for example: 'KB', 'MiB', 'G' and 'B' as number suffixes.

Options which do not take arguments are boolean options, and set the corresponding value to true. They can be set to false by prefixing the option name with "no". For example using "-nofoo" will set the boolean option with name "foo" to false.

### 3.1 Stream specifiers# TOC

Some options are applied per-stream, e.g. bitrate or codec. Stream specifiers are used to precisely specify which stream(s) a given option belongs to.

A stream specifier is a string generally appended to the option name and separated from it by a colon. E.g. -codec:a:1 ac3 contains the a:1 stream specifier, which matches the second audio stream. Therefore, it would select the ac3 codec for the second audio stream.

A stream specifier can match several streams, so that the option is applied to all of them. E.g. the stream specifier in -b:a 128k matches all audio streams.

An empty stream specifier matches all streams. For example, -codec copy or -codec: copy would copy all the streams without reencoding.

Possible forms of stream specifiers are:

stream\_index

Matches the stream with this index. E.g. -threads:1 4 would set the thread count for the second stream to 4.

stream\_type[:stream\_index]

*stream\_type* is one of following: 'v' or 'V' for video, 'a' for audio, 's' for subtitle, 'd' for data, and 't' for attachments. 'v' matches all video streams, 'V' only matches video streams which are not attached pictures, video thumbnails or cover arts. If *stream\_index* is given, then it matches stream number *stream\_index* of this type. Otherwise, it matches all streams of this type.

p:program\_id[:stream\_index]

If *stream\_index* is given, then it matches the stream with number *stream\_index* in the program with the id *program\_id*. Otherwise, it matches all streams in the program.

```
#stream_id or i:stream_id
```

Match the stream by stream id (e.g. PID in MPEG-TS container).

m:key[:value]

Matches streams with the metadata tag key having the specified value. If value is not given, matches streams that contain the given tag with any value.

u

Matches streams with usable configuration, the codec must be defined and the essential information such as video dimension or audio sample rate must be present.

Note that in ffmpeg, matching by metadata will only work properly for input files.

### 3.2 Generic options# TOC

These options are shared amongst the ff\* tools.

-L

Show license.

-h, -?, -help, --help [arg]

Show help. An optional parameter may be specified to print help about a specific item. If no argument is specified, only basic (non advanced) tool options are shown.

Possible values of *arg* are:

long

Print advanced tool options in addition to the basic tool options.

full

Print complete list of options, including shared and private options for encoders, decoders, demuxers, muxers, filters, etc.

#### decoder=decoder\_name

Print detailed information about the decoder named *decoder\_name*. Use the -decoders option to get a list of all decoders.

#### encoder=encoder\_name

Print detailed information about the encoder named *encoder\_name*. Use the -encoders option to get a list of all encoders.

#### demuxer=demuxer\_name

Print detailed information about the demuxer named *demuxer\_name*. Use the -formats option to get a list of all demuxers and muxers.

#### muxer=muxer\_name

Print detailed information about the muxer named *muxer\_name*. Use the -formats option to get a list of all muxers and demuxers.

#### filter=filter\_name

Print detailed information about the filter name *filter\_name*. Use the -filters option to get a list of all filters.

#### -version

Show version.

#### -formats

Show available formats (including devices).

#### -demuxers

Show available demuxers.

#### -muxers

Show available muxers.

#### -devices

Show available devices.

-codecs

Show all codecs known to libavcodec.

Note that the term 'codec' is used throughout this documentation as a shortcut for what is more correctly called a media bitstream format.

#### -decoders

Show available decoders.

#### -encoders

Show all available encoders.

#### -bsfs

Show available bitstream filters.

#### -protocols

Show available protocols.

#### -filters

Show available libavfilter filters.

#### -pix\_fmts

Show available pixel formats.

```
-sample_fmts
```

Show available sample formats.

#### -layouts

Show channel names and standard channel layouts.

#### -colors

Show recognized color names.

```
-sources device[,opt1=val1[,opt2=val2]...]
```

Show autodetected sources of the intput device. Some devices may provide system-dependent source names that cannot be autodetected. The returned list cannot be assumed to be always complete.

```
ffmpeg -sources pulse, server=192.168.0.4
```

```
-sinks device[,opt1=val1[,opt2=val2]...]
```

Show autodetected sinks of the output device. Some devices may provide system-dependent sink names that cannot be autodetected. The returned list cannot be assumed to be always complete.

```
ffmpeg -sinks pulse,server=192.168.0.4
```

```
-loglevel [repeat+] loglevel | -v [repeat+] loglevel
```

Set the logging level used by the library. Adding "repeat+" indicates that repeated log output should not be compressed to the first line and the "Last message repeated n times" line will be omitted. "repeat" can also be used alone. If "repeat" is used alone, and with no prior loglevel set, the default loglevel will be used. If multiple loglevel parameters are given, using 'repeat' will not change the loglevel. *loglevel* is a string or a number containing one of the following values:

'quiet, -8'

Show nothing at all; be silent.

'panic, 0'

Only show fatal errors which could lead the process to crash, such as an assertion failure. This is not currently used for anything.

'fatal, 8'

Only show fatal errors. These are errors after which the process absolutely cannot continue.

```
'error, 16'
```

Show all errors, including ones which can be recovered from.

```
'warning, 24'
```

Show all warnings and errors. Any message related to possibly incorrect or unexpected events will be shown.

```
'info, 32'
```

Show informative messages during processing. This is in addition to warnings and errors. This is the default value.

```
'verbose, 40'
```

Same as info, except more verbose.

'debug, 48'

Show everything, including debugging information.

'trace, 56'

By default the program logs to stderr. If coloring is supported by the terminal, colors are used to mark errors and warnings. Log coloring can be disabled setting the environment variable AV\_LOG\_FORCE\_NOCOLOR or NO\_COLOR, or can be forced setting the environment variable AV\_LOG\_FORCE\_COLOR. The use of the environment variable NO\_COLOR is deprecated and will be dropped in a future FFmpeg version.

#### -report

Dump full command line and console output to a file named *program-YYYYMMDD-HHMMSS*.log in the current directory. This file can be useful for bug reports. It also implies -loglevel verbose.

Setting the environment variable FFREPORT to any value has the same effect. If the value is a ':'-separated key=value sequence, these options will affect the report; option values must be escaped if they contain special characters or the options delimiter ':' (see the "Quoting and escaping" section in the ffmpeg-utils manual).

The following options are recognized:

#### file

set the file name to use for the report; %p is expanded to the name of the program, %t is expanded to a timestamp, %% is expanded to a plain %

#### level

set the log verbosity level using a numerical value (see -loglevel).

For example, to output a report to a file named ffreport.log using a log level of 32 (alias for log level info):

FFREPORT=file=ffreport.log:level=32 ffmpeg -i input output

Errors in parsing the environment variable are not fatal, and will not appear in the report.

-hide\_banner

Suppress printing banner.

All FFmpeg tools will normally show a copyright notice, build options and library versions. This option can be used to suppress printing this information.

```
-cpuflags flags (global)
```

Allows setting and clearing cpu flags. This option is intended for testing. Do not use it unless you know what you're doing.

ffmpeg -cpuflags -sse+mmx ...
ffmpeg -cpuflags mmx ...
ffmpeg -cpuflags 0 ...

Possible flags for this option are:

```
'x86'
    'mmx'
    'mmxext'
    'sse'
    'sse2'
    'sse2slow'
    'sse3'
    'sse3slow'
    'ssse3'
    'atom'
    'sse4.1'
    'sse4.2'
    'avx'
    'avx2'
    'xop'
    'fma3'
    'fma4'
    '3dnow'
    '3dnowext'
    'bmil'
    'bmi2'
    'cmov'
'ARM'
    'armv5te'
    'armv6'
    'armv6t2'
    'vfp'
    'vfpv3'
    'neon'
    'setend'
'AArch64'
    'armv8'
    'vfp'
    'neon'
'PowerPC'
    'altivec'
'Specific Processors'
```

```
'pentium2'
'pentium3'
'pentium4'
'k6'
'k62'
'athlon'
'athlonxp'
'k8'
-opencl_bench
```

This option is used to benchmark all available OpenCL devices and print the results. This option is only available when FFmpeg has been compiled with --enable-opencl.

When FFmpeg is configured with --enable-opencl, the options for the global OpenCL context are set via -opencl\_options. See the "OpenCL Options" section in the ffmpeg-utils manual for the complete list of supported options. Amongst others, these options include the ability to select a specific platform and device to run the OpenCL code on. By default, FFmpeg will run on the first device of the first platform. While the options for the global OpenCL context provide flexibility to the user in selecting the OpenCL device of their choice, most users would probably want to select the fastest OpenCL device for their system.

This option assists the selection of the most efficient configuration by identifying the appropriate device for the user's system. The built-in benchmark is run on all the OpenCL devices and the performance is measured for each device. The devices in the results list are sorted based on their performance with the fastest device listed first. The user can subsequently invoke ffmpeg using the device deemed most appropriate via -opencl\_options to obtain the best performance for the OpenCL accelerated code.

Typical usage to use the fastest OpenCL device involve the following steps.

Run the command:

ffmpeg -opencl\_bench

Note down the platform ID (pidx) and device ID (didx) of the first i.e. fastest device in the list. Select the platform and device using the command:

ffmpeg -opencl\_options platform\_idx=pidx:device\_idx=didx ...

-opencl\_options options (global)

Set OpenCL environment options. This option is only available when FFmpeg has been compiled with --enable-opencl.

*options* must be a list of *key=value* option pairs separated by ':'. See the "OpenCL Options" section in the ffmpeg-utils manual for the list of supported options.

### 3.3 AVOptions# TOC

These options are provided directly by the libavformat, libavdevice and libavcodec libraries. To see the list of available AVOptions, use the -help option. They are separated into two categories:

generic

These options can be set for any container, codec or device. Generic options are listed under AVFormatContext options for containers/devices and under AVCodecContext options for codecs.

private

These options are specific to the given container, device or codec. Private options are listed under their corresponding containers/devices/codecs.

For example to write an ID3v2.3 header instead of a default ID3v2.4 to an MP3 file, use the id3v2\_version private option of the MP3 muxer:

ffmpeg -i input.flac -id3v2\_version 3 out.mp3

All codec AVOptions are per-stream, and thus a stream specifier should be attached to them.

Note: the -nooption syntax cannot be used for boolean AVOptions, use -option 0/-option 1.

Note: the old undocumented way of specifying per-stream AVOptions by prepending v/a/s to the options name is now obsolete and will be removed soon.

### 3.4 Main options# TOC

```
-f format
```

Force format to use.

-unit

Show the unit of the displayed values.

```
-prefix
```

Use SI prefixes for the displayed values. Unless the "-byte\_binary\_prefix" option is used all the prefixes are decimal.

-byte\_binary\_prefix

Force the use of binary prefixes for byte values.

-sexagesimal

Use sexagesimal format HH:MM:SS.MICROSECONDS for time values.

#### -pretty

Prettify the format of the displayed values, it corresponds to the options "-unit -prefix -byte\_binary\_prefix -sexagesimal".

-of, -print\_format writer\_name[=writer\_options]

Set the output printing format.

*writer\_name* specifies the name of the writer, and *writer\_options* specifies the options to be passed to the writer.

For example for printing the output in JSON format, specify:

-print\_format json

For more details on the available output printing formats, see the Writers section below.

-sections

Print sections structure and section information, and exit. The output is not meant to be parsed by a machine.

```
-select_streams stream_specifier
```

Select only the streams specified by *stream\_specifier*. This option affects only the options related to streams (e.g. show\_streams, show\_packets, etc.).

For example to show only audio streams, you can use the command:

ffprobe -show\_streams -select\_streams a INPUT

To show only video packets belonging to the video stream with index 1:

ffprobe -show\_packets -select\_streams v:1 INPUT

-show\_data

Show payload data, as a hexadecimal and ASCII dump. Coupled with -show\_packets, it will dump the packets' data. Coupled with -show\_streams, it will dump the codec extradata.

The dump is printed as the "data" field. It may contain newlines.

```
-show_data_hash algorithm
```

Show a hash of payload data, for packets with -show\_packets and for codec extradata with -show\_streams.

-show\_error

Show information about the error found when trying to probe the input.

The error information is printed within a section with name "ERROR".

-show\_format

Show information about the container format of the input multimedia stream.

All the container format information is printed within a section with name "FORMAT".

-show\_format\_entry name

Like -show\_format, but only prints the specified entry of the container format information, rather than all. This option may be given more than once, then all specified entries will be shown.

This option is deprecated, use show\_entries instead.

```
-show_entries section_entries
```

Set list of entries to show.

Entries are specified according to the following syntax. *section\_entries* contains a list of section entries separated by :. Each section entry is composed by a section name (or unique name), optionally followed by a list of entries local to that section, separated by , .

If section name is specified but is followed by no =, all entries are printed to output, together with all the contained sections. Otherwise only the entries specified in the local section entries list are printed. In particular, if = is specified but the list of local entries is empty, then no entries will be shown for that section.

Note that the order of specification of the local section entries is not honored in the output, and the usual display order will be retained.

The formal syntax is given by:

LOCAL_SECTION_ENTRIES	::= SECTION_ENTRY_NAME[, LOCAL_SECTION_ENTRIES]
SECTION_ENTRY	::= SECTION_NAME[=[LOCAL_SECTION_ENTRIES]]
SECTION_ENTRIES	::= SECTION_ENTRY[:SECTION_ENTRIES]

For example, to show only the index and type of each stream, and the PTS time, duration time, and stream index of the packets, you can specify the argument:

packet=pts\_time,duration\_time,stream\_index : stream=index,codec\_type

To show all the entries in the section "format", but only the codec type in the section "stream", specify the argument:

format : stream=codec\_type

To show all the tags in the stream and format sections:

stream\_tags : format\_tags

To show only the title tag (if available) in the stream sections:

stream\_tags=title

-show\_packets

Show information about each packet contained in the input multimedia stream.

The information for each single packet is printed within a dedicated section with name "PACKET".

-show\_frames

Show information about each frame and subtitle contained in the input multimedia stream.

The information for each single frame is printed within a dedicated section with name "FRAME" or "SUBTITLE".

-show\_streams

Show information about each media stream contained in the input multimedia stream.

Each media stream information is printed within a dedicated section with name "STREAM".

-show\_programs

Show information about programs and their streams contained in the input multimedia stream.

Each media stream information is printed within a dedicated section with name "PROGRAM\_STREAM".

-show\_chapters

Show information about chapters stored in the format.

Each chapter is printed within a dedicated section with name "CHAPTER".

#### -count\_frames

Count the number of frames per stream and report it in the corresponding stream section.

-count\_packets

Count the number of packets per stream and report it in the corresponding stream section.

```
-read_intervals read_intervals
```

Read only the specified intervals. *read\_intervals* must be a sequence of interval specifications separated by ",". ffprobe will seek to the interval starting point, and will continue reading from that.

Each interval is specified by two optional parts, separated by "%".

The first part specifies the interval start position. It is interpreted as an absolute position, or as a relative offset from the current position if it is preceded by the "+" character. If this first part is not specified, no seeking will be performed when reading this interval.

The second part specifies the interval end position. It is interpreted as an absolute position, or as a relative offset from the current position if it is preceded by the "+" character. If the offset specification starts with "#", it is interpreted as the number of packets to read (not including the flushing packets) from the interval start. If no second part is specified, the program will read until the end of the input.

Note that seeking is not accurate, thus the actual interval start point may be different from the specified position. Also, when an interval duration is specified, the absolute end time will be computed by adding the duration to the interval start point found by seeking the file, rather than to the specified start value.

The formal syntax is given by:

```
INTERVAL ::= [START + START_OFFSET] [% [END + END_OFFSET]]
INTERVALS ::= INTERVAL[, INTERVALS]
```

A few examples follow.

• Seek to time 10, read packets until 20 seconds after the found seek point, then seek to position 01:30 (1 minute and thirty seconds) and read packets until position 01:45.

10%+20,01:30%01:45

• Read only 42 packets after seeking to position 01:23:

01:23%+#42

• Read only the first 20 seconds from the start:

%+20

• Read from the start until position 02:30:

%02**:**30

```
-show_private_data, -private
```

Show private data, that is data depending on the format of the particular shown element. This option is enabled by default, but you may need to disable it for specific uses, for example when creating XSD-compliant XML output.

-show\_program\_version

Show information related to program version.

Version information is printed within a section with name "PROGRAM\_VERSION".

-show\_library\_versions

Show information related to library versions.

Version information for each library is printed within a section with name "LIBRARY\_VERSION".

-show\_versions

Show information related to program and library versions. This is the equivalent of setting both -show\_program\_version and -show\_library\_versions options.

```
-show_pixel_formats
```

Show information about all pixel formats supported by FFmpeg.

Pixel format information for each format is printed within a section with name "PIXEL\_FORMAT".

-bitexact

Force bitexact output, useful to produce output which is not dependent on the specific build.

```
-i input_url
```

Read input\_url.

### 4 Writers# TOC

A writer defines the output format adopted by ffprobe, and will be used for printing all the parts of the output.

A writer may accept one or more arguments, which specify the options to adopt. The options are specified as a list of *key=value* pairs, separated by ":".

All writers support the following options:

```
string_validation, sv
```

Set string validation mode.

The following values are accepted.

'fail'

The writer will fail immediately in case an invalid string (UTF-8) sequence or code point is found in the input. This is especially useful to validate input metadata.

'ignore'

Any validation error will be ignored. This will result in possibly broken output, especially with the json or xml writer.

'replace'

The writer will substitute invalid UTF-8 sequences or code points with the string specified with the string\_validation\_replacement.

Default value is 'replace'.

```
string_validation_replacement, svr
```

Set replacement string to use in case string\_validation is set to 'replace'.

In case the option is not specified, the writer will assume the empty string, that is it will remove the invalid sequences from the input strings.

A description of the currently available writers follows.

### 4.1 default# TOC

Default format.

Print each section in the form:

```
[SECTION]
key1=val1
...
keyN=valN
[/SECTION]
```

Metadata tags are printed as a line in the corresponding FORMAT, STREAM or PROGRAM\_STREAM section, and are prefixed by the string "TAG:".

A description of the accepted options follows.

nokey, nk

If set to 1 specify not to print the key of each field. Default value is 0.

noprint\_wrappers, nw

If set to 1 specify not to print the section header and footer. Default value is 0.

### 4.2 compact, csv# TOC

Compact and CSV format.

The csv writer is equivalent to compact, but supports different defaults.

Each section is printed on a single line. If no option is specifid, the output has the form:

section|key1=val1| ... |keyN=valN

Metadata tags are printed in the corresponding "format" or "stream" section. A metadata tag key, if printed, is prefixed by the string "tag:".

The description of the accepted options follows.

item\_sep, s

Specify the character to use for separating fields in the output line. It must be a single printable character, it is "|" by default ("," for the csv writer).

```
nokey, nk
```

If set to 1 specify not to print the key of each field. Its default value is 0 (1 for the csv writer).

escape, e

Set the escape mode to use, default to "c" ("csv" for the csv writer).

It can assume one of the following values:

С

Perform C-like escaping. Strings containing a newline ('\n'), carriage return ('\r'), a tab ('\t'), a form feed ('\f'), the escaping character ('\') or the item separator character *SEP* are escaped using C-like fashioned escaping, so that a newline is converted to the sequence '\n', a carriage return to '\r', '\' to '\\' and the separator *SEP* is converted to '\*SEP*'.

csv

Perform CSV-like escaping, as described in RFC4180. Strings containing a newline ('\n'), a carriage return ('\r'), a double quote ('"'), or *SEP* are enclosed in double-quotes.

none

Perform no escaping.

print\_section, p

Print the section name at the begin of each line if the value is 1, disable it with value set to 0. Default value is 1.

### 4.3 flat# TOC

Flat format.

A free-form output where each line contains an explicit key=value, such as "streams.stream.3.tags.foo=bar". The output is shell escaped, so it can be directly embedded in sh scripts as long as the separator character is an alphanumeric character or an underscore (see *sep\_char* option).

The description of the accepted options follows.

sep\_char, s

Separator character used to separate the chapter, the section name, IDs and potential tags in the printed field key.

Default value is '.'.

hierarchical, h

Specify if the section name specification should be hierarchical. If set to 1, and if there is more than one section in the current chapter, the section name will be prefixed by the name of the chapter. A value of 0 will disable this behavior.

Default value is 1.

### **4.4 ini# TOC**

INI format output.

Print output in an INI based format.

The following conventions are adopted:

- all key and values are UTF-8
- '.' is the subgroup separator
- newline, '\t', '\f', '\b' and the following characters are escaped
- '\' is the escape character
- '#' is the comment indicator
- '=' is the key/value separator

• ':' is not used but usually parsed as key/value separator

This writer accepts options as a list of key=value pairs, separated by ':'.

The description of the accepted options follows.

```
hierarchical, h
```

Specify if the section name specification should be hierarchical. If set to 1, and if there is more than one section in the current chapter, the section name will be prefixed by the name of the chapter. A value of 0 will disable this behavior.

Default value is 1.

### 4.5 json# TOC

JSON based format.

Each section is printed using JSON notation.

The description of the accepted options follows.

compact, c

If set to 1 enable compact output, that is each section will be printed on a single line. Default value is 0.

For more information about JSON, see http://www.json.org/.

### **4.6 xml# TOC**

XML based format.

The XML output is described in the XML schema description file ffprobe.xsd installed in the FFmpeg datadir.

An updated version of the schema can be retrieved at the url http://www.ffmpeg.org/schema/ffprobe.xsd, which redirects to the latest schema committed into the FFmpeg development source code tree.

Note that the output issued will be compliant to the ffprobe.xsd schema only when no special global output options (unit, prefix, byte\_binary\_prefix, sexagesimal etc.) are specified.

The description of the accepted options follows.

```
fully_qualified, q
```

If set to 1 specify if the output should be fully qualified. Default value is 0. This is required for generating an XML file which can be validated through an XSD file.

```
xsd_compliant, x
```

If set to 1 perform more checks for ensuring that the output is XSD compliant. Default value is 0. This option automatically sets fully\_qualified to 1.

For more information about the XML format, see http://www.w3.org/XML/.

## 5 Timecode# TOC

ffprobe supports Timecode extraction:

- MPEG1/2 timecode is extracted from the GOP, and is available in the video stream details (-show\_streams, see *timecode*).
- MOV timecode is extracted from tmcd track, so is available in the tmcd stream metadata (-show\_streams, see *TAG:timecode*).
- DV, GXF and AVI timecodes are available in format metadata (-show\_format, see *TAG:timecode*).

## 6 See Also# TOC

ffprobe-all, ffmpeg, ffplay, ffserver, ffmpeg-utils, ffmpeg-scaler, ffmpeg-resampler, ffmpeg-codecs, ffmpeg-bitstream-filters, ffmpeg-formats, ffmpeg-devices, ffmpeg-protocols, ffmpeg-filters

# 7 Authors# TOC

The FFmpeg developers.

For details about the authorship, see the Git history of the project (git://source.ffmpeg.org/ffmpeg), e.g. by typing the command git log in the FFmpeg source directory, or browsing the online repository at http://source.ffmpeg.org.

Maintainers for the specific components are listed in the file MAINTAINERS in the source code tree.

This document was generated using makeinfo.